


## 7 Compile and Test the Touch Keyboard

### Compiling your Keyboard

Now click Save to save your work, and compile the keyboard, using one of the following methods:

- Build tab, Compile Keyboard button
- Keyboard menu, Compile Keyboard menu item
- F7 shortcut key

Hopefully you'll see it compiled with no error messages:



```
Messages
fulfulde.kmn: Compiling 'G:\My Drive\2020-02 Keyman Workshop Participant Keyboards\F
fulfulde.kmn: Success: 'G:\My Drive\2020-02 Keyman Workshop Participant Keyboards\Rc
fulfulde.kmn: Compiling 'G:\My Drive\2020-02 Keyman Workshop Participant Keyboards\F
fulfulde.kmn: Success: 'G:\My Drive\2020-02 Keyman Workshop Participant Keyboards\Rc
```

### Errors when Compiling?

You might see a warning like:

*Warning: line 0 warning 2092: Key "T\_new\_579" on layer "default", platform "phone", is a custom key but has no corresponding rule in the source.*

This shows you forgot to enter the correct keycode for a new key you added. Double-check your longpress popup keys for one with a “T\_new\_NNN” code (T\_new\_579 in this example), and add in the desired “U\_NNNN” code.

The purpose of the T\_new\_NNN codes is so that you can write rules for these keys in the same way you do for physical keys. If you add these key references (which you can customize to anything, like T\_Hook\_Y\_UC) to the code, then you can make rules for them alongside your physical keyboard rules in the kmn coding section.

You might also see a message like

*Error: line 0 error 405A: Key "U+0181" on "phone", layer "default" has an invalid identifier.*

This shows you attempted to change the keycode but mistyped the code. I’ve gotten this more than once because I am used to typing U+0181 to refer to a Unicode value, but the correct syntax for a keycode in Keyman Developer is **U\_0181**.


### Testing your keyboard

**See also [the Keyman help page on testing keyboards](#)**

The “Test Keyboard” command under the “Keyboard” menu only tests the desktop versions of a keyboard, not the mobile versions. To test a mobile keyboard, you can use the Chrome browser on your Windows computer to simulate a mobile device.

### The Build Tab

To do this, go to the Build tab (bottom one in the left column) and in the “Web and Mobile targets” box, click “Test keyboard on web”. Now click “Open debugger in local browser.”



## Testing in Chrome


Your default browser will open with the keyboard.

If your default browser is not Chrome, this may or may not work. If it doesn't, you will need to copy the URL and paste it into Chrome.

1. The default web keyboard is displayed

It opens with a Keyboard Test Host window showing a visual keyboard. Don't worry, this is not your touch keyboard, but the web version of your desktop keyboard.

# Keyboard Test Host




## 2. Open Chrome's web developer tools

Chrome can simulate a mobile device. Press F12 or Ctrl-Shift-i to open the web developer tools, and a panel will open on the right.


## 3. Open the Mobile Toolbar





#### 4. Select your test device


As shown above, click on the Toggle device button. You will get a device selection bar at the top of the



screen like this: 🗑️

Now the “Keyboard test host” panel should shrink in size

5. Refresh the page

You must click the curling arrow  (or press the F5 key) to reload the page in Chrome before you see the mobile keyboard layout. When you see a button saying “Install Keyman for Android” (or “Install Keyman for iOS”), you have gotten to the right setup.

6. Click in the yellow box

Now the mobile keyboard layout should appear below. Your cursor has changed to a gray circle representing the size of a fingertip on a mobile keyboard. You should be able to test the keyboard now. Click on any key to make a simple press of that key, click and hold to make a longpress on a key. (If you're using a touch pad rather than an actual mouse, tap the pad for a simple press and double tap and hold for longpress.)

# Keyboard Test Host

Install Keyman for Android

Add keyboard to Keyman for Android

-

empty

[Empty text area with a cursor and a grey dot]

